



## Laboratory Testing for Urinary Tract Infection and Asymptomatic Bacteriuria

### SYNOPSIS AND RELEVANCE

There are a variety of clinical scenarios where testing may be indicated to diagnose a urinary tract infection (UTI) or asymptomatic bacteriuria (ASB). Utilizing the appropriate test(s) on the appropriate patient can:

1. Facilitate prompt, appropriate treatment to prevent complications and relieve symptoms.
2. Avoid unnecessary antibiotic therapy to protect patients from side effects and minimize the emergence of antimicrobial resistant strains.
3. Advance diagnostic stewardship.
4. Minimize catheter-associated UTI (CAUTI) rates.

### INSIGHTS

1. Female patients presenting with symptoms of acute simple cystitis do not require laboratory testing .
2. Urine culture is indicated for patients who meet clinical criteria for a complicated UTI.
3. Urine culture to screen for ASB is indicated during pregnancy and prior to an endoscopic urologic procedure associated with mucosal disruption.
4. Transferring urine specimens to a boric acid preservative tube is a best practice that ensures accurate quantitation of bacteria recovered in culture since the acceptable alternative (continual refrigeration from 30 min of collection to time of processing) is difficult to achieve.

### BACKGROUND

Urinary tract infections (UTIs) account for a large portion of antibiotic use in humans that contributes to the emergence and spread of multi-drug resistant organisms.<sup>1</sup> Types of UTI include cystitis (confined to the bladder) and pyelonephritis (extension to the upper urinary tract).<sup>2</sup> Clinical features of cystitis include pyuria, dysuria, frequency, urgency, and suprapubic pain. Patients with pyelonephritis typically present with fever, chills, flank pain, and costovertebral angle tenderness. To regulate drug development and labeling, the FDA makes a distinction between uncomplicated and complicated UTIs. Uncomplicated UTI is acute cystitis in a female with normal anatomy lacking systemic signs attributed to pyelonephritis.<sup>3</sup> Complicated UTI is defined as signs or symptoms of pyelonephritis or systemic infection or UTI in a patient with an anatomic or neurologic abnormality of the urinary tract (eg, indwelling urinary catheter, obstruction, renal failure) or significant immunocompromise that increases the likelihood of treatment failure or a serious outcome.<sup>1,2,4</sup> Despite limitations (slow turnaround time, low specificity, bias toward common uropathogens), culture remains the gold standard test for UTI and one of the highest volume tests performed in microbiology laboratories.<sup>1</sup>

Asymptomatic bacteriuria (ASB) is defined as the recovery of  $\geq 100,000$  colony-forming units (CFU)/ml bacteria from a urine culture performed on a patient lacking signs and symptoms of UTI.<sup>5</sup> Screening for ASB is only recommended during pregnancy and prior to an endoscopic urologic procedure associated with mucosal disruption. Antimicrobial treatment of ASB in pregnancy, reduces the risk of pyelonephritis, preterm labor, and low birth weight. Lithotripsy and transurethral surgery of the prostate are examples of invasive urologic procedures for which preoperative ASB screening and treatment can prevent post-surgical infectious complications.

One of the most common infections that can be acquired during hospitalization is UTI, and the major risk factor is presence of an indwelling urinary catheter.<sup>6</sup> Catheter-associated urinary tract infections (CAUTIs) are a mandated quality measure reported to the National Healthcare Safety Network and defined by at least one UTI symptom and  $\geq 100,000$  CFU/ml of a uropathogen from a urine culture.<sup>7</sup> Preventing CAUTI has been a high priority for healthcare institutions for the past decade to reduce potential complications and associated healthcare costs. Key principles to prevent CAUTIs include 1) avoid unnecessary catheter placement, 2) ensure catheter placement is performed using sterile technique, and 3) frequent reassessment of continued need for catheter with prompt removal.<sup>8,9</sup>

Culturing urine for bacteria is useful in the diagnosis and treatment of UTI and ASB. Urine within the bladder is normally a sterile body fluid. However, resident microbiota from the perineum, urethra, and vagina often contaminate urine specimens. Quantitation of bacteria in urine cultures helps the laboratory to distinguish contaminated specimens from those representing infection, but a key preanalytic principle is for clinicians to only order culture on patients who should be screened for ASB or have signs and symptoms of UTI. Female outpatients presenting with classic symptoms of uncomplicated cystitis usually do not need laboratory testing unless there are risk factors for antimicrobial resistance.<sup>2</sup> When urine culture is indicated, attention to preanalytical aspects (sample collection, use of a preservative or refrigeration, prompt processing) is of utmost importance. Cleansing prior to collection of

“midstream” urine is recommended even though evidence to support this practice is lacking.<sup>10</sup> Accurate quantitation of growth is fostered by placement of urine specimens in boric acid preservative or refrigeration within 30 minutes of collection.<sup>11</sup> A primary advantage of refrigeration is the lack of interference with other assays that may be ordered on urine. Delayed processing of samples held at room temperature has been associated with increases in culture colony counts of 10% after 4 hours and >135% after 24 hours.<sup>10</sup> Increased transit time due to consolidation of laboratory services led many large healthcare systems to require boric acid preservative of urine submitted for culture since continual refrigeration and processing within 24 hours after collection can be difficult to achieve. Use of boric acid preservative as an alternative to refrigeration extends the time allowed between collection and processing for culture to 48 hours.

The quantitative threshold applied by clinical microbiology laboratories for susceptibility testing of potential uropathogens is usually 100,000 CFU/ml in a midstream voided specimen. However, lower quantities of 1000 CFU/ml may represent infection. The most common uropathogens are resident intestinal microbiota organisms (*Escherichia coli*, *Klebsiella* spp., *Enterobacter* spp., *Proteus* spp. and *Enterococcus* spp.). The level of work up (identification and susceptibility testing) performed on a urine culture is based on the type of specimen (invasive collection or voided), the number of different organisms growing, and the quantity of potential uropathogens in relation to usual skin/urogenital microbiota.<sup>11</sup>

Some healthcare systems offer clinicians the option of ordering a reflex testing algorithm that begins with urinalysis (UA); urine culture is performed only if certain criteria are met. Experts agree that urine leukocyte count of 10 per high power field is an appropriate threshold for UA reflex to culture if the algorithm test is ordered (experts disagree regarding the utility of leukocyte esterase or nitrate as the threshold for reflex to culture).<sup>12</sup> Most patients with UTI will have a positive UA, but the sensitivity of pyuria for UTI is lower if the etiology is enterococci or yeast. Since pyuria cannot distinguish ASB from UTI, clinical signs and symptoms (rather than UA) should be the basis of whether a urine culture is ordered.<sup>12</sup> Ordering a reflex urine culture for a patient lacking UTI symptoms often leads to unnecessary antimicrobial therapy.<sup>13</sup> Clinical decision support tools for UTI to guide urine culture ordering are being implemented in many institutions to optimize antimicrobial stewardship and minimize CAUTI rates.

## REFERENCES

1. Patel R, Polage CR, Dien Bard J, May L, Lee FM, Fabre V, Hayden MK, Doernberg SDB, Haake DA, Trautner BW, Grigoryan L, Tsalik EL, Hanson KE. Envisioning Future Urinary Tract Infection Diagnostics. *Clin Infect Dis*. 2022;74:1284 -1292.
2. Gupta K, Hooton TM, Naber KG, et al.. Infectious Diseases Society of America; European Society for Microbiology and Infectious Diseases. International clinical practice guidelines for the treatment of acute uncomplicated cystitis and pyelonephritis in women: A 2010 update by the Infectious Diseases Society of America and the European Society for Microbiology and Infectious Diseases. *Clin Infect Dis*. 2011;52(5):e103 - e120. doi:10.1093/cid/ciq257
3. United States Food and Drug Administration, Center for Drug Evaluation and Research (CDER). Uncomplicated urinary tract infections: Developing drugs for treatment guidance for industry. August 2019. Accessed December 18, 2023. <https://www.fda.gov/media/129531/download>
4. United States Food and Drug Administration, Center for Drug Evaluation and Research (CDER). Complicated urinary tract infections: Developing drugs for treatment guidance for industry. June 2018. Accessed December 18, 2023. <https://www.fda.gov/media/71313/download>
5. Nicolle LE, Gupta K, Bradley SF, et al. Clinical practice guideline for the management of asymptomatic bacteriuria: 2019 update by the Infectious Diseases Society of America. *Clin Infect Dis*. 2019;68(10):e83-e110. doi:10.1093/cid/ciy1121
6. Lo, E, Nicolle, L, Coffin, et al. (2014). Strategies to Prevent Catheter-Associated Urinary Tract Infections in Acute Care Hospitals: 2014 update. *Infection Control & Hospital Epidemiology*.2014;35(5):464 - 479. doi:10.1086/675718
7. Center for Disease Control and Prevention. National Healthcare Safety Network (NHSN). Urinary tract infection (Catheter-associated urinary tract infection [CAUTI] and non-catheter-associated urinary tract infection [UTI] events. January 2023. Accessed December 18, 2023. <https://www.cdc.gov/nhsn/pdfs/pscmanual/7pscaccuticurrent.pdf>
8. Saint S, Greene MT, Krein SL, et al . A program to prevent catheter-associated urinary tract infection in acute care. *N Engl J Med*. 2016;37:2111.
9. Mullin KM, Kovacs CS, Fatica C, et al. A Multifaceted Approach to Reduction of Catheter-Associated Urinary Tract Infections in the Intensive Care Unit With an Emphasis on "Stewardship of Culturing". *Infect Control Hosp Epidemiol*. 2017;38(2):186 -188.
10. LaRocco MT, Franek J, Leibach EK, et al. Effectiveness of Preanalytic Practices on Contamination and Diagnostic Accuracy of Urine Cultures: a Laboratory Medicine Best Practices Systematic Review and Meta-analysis. *Clin Microbiol Rev*. 2016 ;29(1):105-147. doi:10.1128/CMR.00030-15.
11. Miller JM, Binnicker MJ, Campbell S, et al. A guide to utilization of the microbiology laboratory for diagnosis of

- infectious diseases: 2018 update by the Infectious Diseases Society of America (IDSA) and the American Society of Microbiology (ASM). *Clin Infect Dis.* 2018; 67:813 - 816.
12. Claeys KC, Trautner BW, Leekha S, et al. Optimal Urine Culture Diagnostic Stewardship Practice-Results from an Expert Modified-Delphi Procedure. *Clin Infect Dis.* 2022;75(3):382 - 389. S
  13. Humphries RM, Dien Bard J. Point-counterpoint: reflex cultures laboratory workload and improve antimicrobial stewardship in patients suspected of having urinary tract infections. *J Clin Microbiol.* 2016;54(2):254 - 258. doi:10.1128/JCM.03021-15.